



January 8, 2014

Document # SB-2285

Service Bulletin

TCS - Titan Control Software v3.0.7

Applicability: This new release is recommended for all Titan product users

Description: Titan Control Software (TCS) version 3.0.7 incorporates the following feature enhancements and bug fixes:

1. Increases the maximum number of supported Titan Input Modules to 64 (up to 1024 channels total)
2. Corrects an error where CPU files with creation dates more than 6 months old did not appear in the 'Browse Remote Files' list
3. Corrects an error that caused all file dates on the CPU to appear to be created in the current year
4. Changes the parsing of the NEMA GPS \$GPRMC message to recognize 3 digits after the decimal point in the timestamp

The new version is available as an *Installer* that includes all required support files as well as an update to the embedded User Manual that provides context-sensitive help.

Update: Download TCS v3.0.7 from the Mars Labs Knowledge Base:

<http://marslabs.com/wiki/doku.php>

Note that you will need a login name and password to download the update – please contact Mars Labs to obtain login credentials if you have not already been supplied the information.

Help: For additional information or assistance, please contact:

Mars Labs
Ph: 301-470-3278
Email: support@marslabs.com

www.marslabs.com