



Mars Labs
29 C Street
Laurel, MD 20707

November 27, 2017

Document # SB-2379

Service Bulletin

TCS - Titan Control Software v3.3.3

Applicability: This new release is recommended for all TCS users.

Description: Titan Control Software version 3.3.3 incorporates the following feature enhancements and bug fixes:

1. Implemented a File Renaming feature that allows renamed files to be read and displayed in TCS.
2. Added serial data rate support for CAI Mini-Recorders.
3. Added a lockout with message if more than one device selects a Digital Pod.
4. When enabled, CPU Monitor Mode is highlighted in yellow with a message indicating that modules are no longer synchronized by the CPU clock.
5. Implemented a prototype WFT-based speed on the In-Vehicle Display targeting an averaged speed from all four wheels at a 5Hz update rate.

TCS v3.3.3 is available as an *Installer* that includes all required support files as well as an update to the embedded User Manual that provides context-sensitive help.

Update: Download TCS v3.3.3 from the Mars Labs Knowledge Base:

<http://marslabs.com/wiki/doku.php>

Note that you will need a login name and password to download the update – please contact Mars Labs to obtain login credentials if you have not already been supplied the information.

Help: For additional information or assistance, please contact:

Mars Labs
Phone: 301-470-3278
Email: support@marslabs.com
www.marslabs.com